Package 'Rdsdp'

October 12, 2022

Version 1.0.5.2

Title R Interface to DSDP Semidefinite Programming Library

Author Zhisu Zhu, Yinyu Ye (DSDP by Steve Benson, Yinyu Ye and Xiong Zhang)

Maintainer Zhisu Zhu <zhuzhisu@alumni.stanford.edu>

Description R interface to DSDP semidefinite programming library. The DSDP software is a free open source implementation of an interior-point method for semidefinite programming. It provides primal and dual solutions, exploits low-rank structure and sparsity in the data, and has relatively low memory requirements for an interior-point method.

Imports utils, methods

LazyLoad yes

License GPL-3

URL

NeedsCompilation yes

Repository CRAN

Date/Publication 2022-05-24 19:50:05 UTC

R topics documented:

| Rdsdp | *R interface to DSDP semidefinite programming library* |

Description

Rdsdp is the R package providing a R interface to DSDP semidefinite programming library. The DSDP package implements a dual-scaling algorithm to find solutions (X, y) to linear and semidefinite optimization problems of the form

$$\text{(P) } \inf \text{ tr}(CX)$$

$$\text{subject to } \mathcal{A}X = b$$

$$X \succeq 0$$

with $(\mathcal{A}X)_i = \text{tr}(A_i X)$ where $X \succeq 0$ means X is positive semidefinite, C and all A_i are symmetric matrices of the same size and b is a vector of length m.

The dual of the problem is

$$\text{(D) } \sup b^T y$$

$$\text{subject to } \mathcal{A}^* y + S = C$$

$$S \succeq 0$$

where $\mathcal{A}y = \sum_{i=1}^{m} y_i A_i$.

Matrices C and A_i are assumed to be block diagonal structured, and must be specified that way (see Details).

References

- https://www.mcs.anl.gov/hs/software/DSDP/

- Steven J. Benson and Yinyu Ye:
  Algorithm 875: DSDP5 software for semidefinite programming ACM Transactions on Mathematical Software (TOMS) 34(3), 2008
  http://web.stanford.edu/~yyye/DSDP5-Paper.pdf

- Steven J. Benson and Yinyu Ye and Xiong Zhang:
  Solving Large-Scale Sparse Semidefinite Programs for Combinatorial Optimization SIAM Journal on Optimization 10(2):443-461, 2000
  http://web.stanford.edu/~yyye/yyye/largesdp.ps.gz

Rdsdp::dsdp   *Solve semidefinite programm with DSDP*

Description

Interface to DSDP semidefinite programming library.

Usage

```
dsdp(A,b,C,K,OPTIONS=NULL)
```

Arguments

A
: An object of class "matrix" with m rows defining the block diagonal constraint matrices A_i. Each constraint matrix A_i is specified by a row of A as explained in the Details section.

b
: A numeric vector of length m containg the right hand side of the constraints.

C
: An object of class "matrix" with one row or a valid class from the class hierarchy in the "Matrix" package. It defines the objective coefficient matrix C with the same structure of A as explained above.

K
: Describes the sizes of each block of the sdp problem. It is a list with the following elements:

   "s": A vector of integers listing the dimension of positive semidefinite cone blocks.

   "l": A scaler integer indicating the dimension of the linear nonnegative cone block.

OPTIONS
: A list of OPTIONS parameters passed to dsdp. It may contain any of the following fields:

   print: = k to display output at each k iteration, else = 0 [default 10].

   logsummary: = 1 print timing information if set to 1.

   save: to set the filename to save solution file in SDPA format.

   outputstats: = 1 to output full information about the solution statistics in STATS.

   gaptol: tolerance for duality gap as a fraction of the value of the objective functions [default 1e-6].

   maxit: maximum number of iterations allowed [default 1000].

   Please refer to DSDP User Guide for additional OPTIONS parameters available.

Details

All problem matrices are assumed to be of block diagonal structure, the input matrix A must be specified as follows:

1. The coefficients for nonnegative cone block are put in the first K$l columns of A.

2. The coefficients for positive semidefinite cone blocks are put after nonnegative cone block in the the same order as those in K\$s. The ith positive semidefinite cone block takes (K\$s)[i] times (K\$s)[[i]] columns, with each row defining a symmetric matrix of size (K\$s)[[i]].

This function does not check for symmetry in the problem data.

Value

Returns a list of three objects:

X	Optimal primal solution X. A vector containing blocks in the same structure as explained above.
y	Optimal dual solution y. A vector of the same length as argument b
STATS	A list with three to eight fields that describe the solution of the problem:

      stype: PDFeasible if the solutions to both (D) and (P) are feasible, Infeasible if (D) is infeasible, and Unbounded if (D) is unbounded.

      dobj: objective value of (D).

      pobj: objective value of (P).

      r: the multiple of the identity element added to $C - \mathcal{A}^* y$ in the final solution to make S positive definite.

      mu: the final barrier parameter ν.

      pstep: the final step length in (P)

      dstep: the final step length in (D)

      pnorm: the final value $\|P(\nu)\|$.

      The last five fields are optional, and only available when OPTIONS\$outputstats is set to 1.

References

• Steven J. Benson and Yinyu Ye:
  DSDP5 User Guide — Software for Semidefinite Programming Technical Report ANL/MCS-TM-277, 2005
  https://www.mcs.anl.gov/hs/software/DSDP/DSDP5-Matlab-UserGuide.pdf

Examples

```
K=NULL
K$s=c(2,3)
K$l=2

C=matrix(c(0,0,2,1,1,2,c(3,0,1,
                         0,2,0,
                         1,0,3)),1,15,byrow=TRUE)
A=matrix(c(0,1,0,0,0,0,c(3,0,1,
                           0,4,0,
                           1,0,5),
           1,0,3,1,1,3,rep(0,9)), 2,15,byrow=TRUE)
b <- c(1,2)
```

```
OPTIONS=NULL
OPTIONS$gaptol=0.000001
OPTIONS$logsummary=0
OPTIONS$outputstats=1

result = dsdp(A,b,C,K,OPTIONS)
```

Rdsdp::dsdp.readsdpa   *Solving semidefinite programs reading from SDPA format files.*

Description

Function to read the semidefinite program input data in SDPA format and solve it.

Usage

```
dsdp.readsdpa(sdpa_filename, options_filename="")
```

Arguments

sdpa_filename   The location of the SDPA input file.

options_filename

          The location of the OPTIONS file [default ""].

Index